

Lunch Sack TUTORIAL

STEP 1: CUT OUT FABRIC



- CUT 4 11" x 19" RECTANGLES, 2 FROM LINING AND 2 FROM MAIN FABRIC
- CUT 2 10" x 7" RECTANGLES OUT OF MAIN FABRIC FOR THE OUTSIDE POCKETS
- CUT 2 6" x 8" RECTANGLES OUT OF LINING FABRIC FOR THE LINING POCKETS
- CUT 1 2" x 12" RECTANGLE OUT OF MAIN FABRIC FOR WRISTLET
- CUT 2 1.5" x 6" RECTANGLES OUT OF MAIN FABRIC FOR VELCRO ENCLOSURE

STEP 2: SEW POCKETS, ENCLOSURE AND WRISTLET

- SEW THE POCKETS RIGHT SIDES TOGETHER, LEAVING AN OPENING ON THE SHORT SIDE (I LEFT THE OPENING ON THE OUTSIDE POCKET UNSEWN AND WILL SEW IT SHUT WHEN I ASSEMBLE THE BAG)
- CLIP CORNERS AND TURN RIGHT SIDE OUT, IRON
- FOLD THE WRISTLET MATERIAL IN HALF, IRON, THEN FOLD IN RAW EDGES AND IRON. SEW UP THE SIDES (FINAL MEASUREMENT WILL BE .5" x 12")
- SEW ENCLOSURE PIECE RIGHT SIDES TOGETHER, ROUNDING THE CORNERS AND LEAVING AN OPENING AT ONE END. TURN RIGHT SIDE OUT, IRON AND TOPSTITCH.

STEP 3: SEW VELCRO

- SEW TACKY VELCRO SIDE ON THE ENCLOSURE PIECE
- SEW SOFT VELCRO SIDE IN THE MIDDLE OF THE FRONT POCKET ABOUT 2" DOWN FROM THE TOP



STEP 4: SEW EXTERIOR

- SEW EXTERIOR POCKET ON, CENTER THE POCKET AND MATCH UP THE BOTTOM OF THE OUTSIDE PIECE TO THE BOTTOM OF THE POCKET.
- SEW ON VELCRO ENCLOSURE, ON THE OTHER PIECE OF FABRIC, MEASURE FROM THE BOTTOM 10.5 INCHES (AND CENTER) AND SEW INTO PLACE
- PIN WRISTLET INTO PLACE
- SEW RIGHT SIDES TOGETHER (MINUS THE OPENING, OF COURSE)



STEP 5: BOX UP THE BOTTOM

- MATCH UP SEAMS (SIDE SEAM AND BOTTOM) AND MEASURE FROM THE CORNER 2 INCHES, MARK PIN AND SEW (SEE PHOTOS)
- DO THIS ON BOTH CORNERS



STEP 6: SEW LINING

- MEASURE 4 INCHES FROM THE BOTTOM, PIN AND SEW THE INTERIOR POCKET ON
- SEW RIGHT SIDES TOGETHER (MINUS THE OPENING, OF COURSE)
- BOX UP THE CORNERS FOR THE LINING (REPEAT STEP 5 FOR THE LINING)

STEP 7: PLEATS AND FINISH

- TURN LINING RIGHT SIDE OUT AND EXTERIOR INSIDE OUT
- NEST EXTERIOR INSIDE THE LINING, PIN AND SEW, LEAVING A 4 INCH GAP TO TURN EVERYTHING RIGHT SIDE IN
- TURN IT ALL RIGHT SIDE IN, IRON AND TOPSTITCH
- MEASURE 2 INCHES ON EITHER SIDE OF THE SEAMS AND MARK A 2 INCH LINE
- FOLD OVER, PIN AND STITCH DOWN 2 INCHES
- REPEAT FOR ALL 4 SIDES

STEP 8: ENJOY!!

